亞洲大學校園網路代理伺服器
The Proxy Server at Asia University

<English in page 2>

1. 亞洲大學提供對外網頁代理服務(proxy service)。
2. 校園網路內實體連線的設備均可使用。
   (不含SSL-VPN設備與安全管制區域設備)
3. 亞洲大學代理伺服器**proxy.asia.edu.tw:3128**
4. 頻寬為共享，請勿佔用。

代理伺服器設定方式 – 以windows 11 25H2 為例

1. 開啟「設定」，選擇「網路和網際網路」，點擊右方「Proxy」
2. 關閉「自動Proxy設定」區域的「自動偵測設定」
   按下「手動Proxy設定」區域的「設定」

3. 在「使用Proxy伺服器」項目，點選為開啟。
   填入代理伺服器位址與埠號，按下「儲存」即可完成。

4. 不使用時請將「使用Proxy伺服器」項目變更為關閉。

※使用代理伺服器，將無法連線校內的網頁及系統 (因為校內系統有管制可連線的IP)。

亞洲大學校園網路代理伺服器
The Proxy Server at Asia University

<繁體中文在第1頁>

1. Asia University provides an external web proxy service.
2. Any device with a physical connection within the campus network can use this service. (Excluding SSL-VPN devices and devices in security-controlled areas)
3. Asia University proxy server: **proxy.asia.edu.tw:3128**.
4. This bandwidth is shared; please do not occupy it.

Proxy server configuration method – taking Windows 11 25H2 as an example

1. Open "Settings," select "Network & Internet," and click "Proxy" on the right side of the page.
2. Turn off “Automatic Proxy Settings” in the “Automatic Proxy Settings” section. Then, click “Set up" in the "Manual Proxy Settings" section.



3. In the "Use Proxy Server" section, select "Enable". Enter the proxy server address and port number, and click "Save" to complete the process.



4. Please turn off the "Use Proxy Server" option when not in use.
   ※Using a proxy server will prevent you from connecting to campus websites and systems (because campus systems restrict the IP addresses that can connect).